

# *Nuclear Fission in the Home Radiation Lab*

By George Dowell

SF, Spontaneous Fission is a form of radioactive decay that is possible in very heavy atoms. Theoretically it can happen in all atoms above  $A=100$ , but in practice SF is only probable in atoms above  $A=230$ .

Elements U-235 ( $2.0 \times 10^{-7}\%$ ), U-238 ( $5.4 \times 10^{-5}\%$ ), Pu-239 ( $4.4 \times 10^{-10}\%$ ), Pu-240 ( $5.0 \times 10^{-6}\%$ ) and Cf-252 (3.09 %) are all candidates for SF, with Cf-252 far and away the most prodigious with fission probability of 3.09% per decay.

Neutron "background" baseline established over several days of monitoring with the Fast Neutron Bubble Detector.

At our altitude of 600 ft., temperature of 73 F and 48 hours, no bubbles were noted. Geology in this region, N.E. Missouri USA, is limestone, from the sediment of an ancient inland sea.

SF Source is a Depleted Uranium collimator weighing 1 pound 12 ounces, the detector being a BTI BD-PND bubble detector. Calculated neutron yield for this mass is 11 n/s.


Fig.1 DU target (left)



Fig.2 Indelible notice required on DU items.



Fig.3 At a distance of 2.5 cm (DU alone), bubbles run 4 or 5 per day.



## **INDUCED FISSION in the HOME RAD LAB Subcritical Neutron Multiplication**

Described is a lab procedure for splitting of U-235 atoms and recording the results in terms of fast neutrons via BTI Bubble Detector Model BD PND.

By experiment we have verified that the BD PND only responds to fast neutrons, not slow neutrons, and also that there are zero "background" neutrons at this location. Spontaneous fission from the DU slab has been documented and is subtracted from the overall results, although the number of SF neutrons is quite small.

Fast initiator neutrons are provided by a lab assembled Ra-Be generator, constructed for the project from radium watch hands plus elemental beryllium.

Yield was about 240 CPM into a moderated and reflected 20 atmosphere He3 neutron detector. This source was temporary and has since been dismantled.

Fast neutrons are first thermalized (slowed down) by layers of high density polyethylene plastic, called HDPE from here on, a hydrogen rich material.

A beam of slowed neutrons is presented to a DU metal target (**note 1**) consisting of approximately 1.75 pounds of U-238 and about 1.2 grams of U-235.

When a neutron is absorbed by a U-235 atom, the atom becomes unstable U-236 and immediately fissions via one of several methods shown below. Each of the methods results in the release of either 2 or 3 fast neutrons, therefore we use the average figure of 2.5 released neutrons in the formula.

We have now multiplied the original fast neutron from the a-Be source to 2.5 neutrons. By judicious use of HDPE moderators and graphite reflector slabs, some of the extra neutrons are slowed and reflected back to be themselves presented to

the DU target. These new neutrons help continue the subcritical multiplication process.

$\alpha + \text{Be} = 1n$  (fast)

Fast  $n + \text{HDPE} = 1n$  (thermal)

Thermal  $n + \text{U-235} = \text{U-236} = \text{Kr-92} + \text{Ba-141}$  (note 2) + 2.5  $n$  (average, Fast)


2.5 Fast  $n + \text{HDPE} + \text{C}$  (reflector) = 2.5  $n$  (slow)

2.5 Thermal  $n + \text{U-235} \dots \text{etc.etc.} = \text{many } n$  (fast) for detection via BTI Bubble detector. Regular U metal (non-DU) impossible to find today. DU easy to find, various forms. DU contains about .2% U-235.

HDPE and are 6" x 6" x .5" slabs, making adjustable piles and taking measurements eventually yields a standard configuration. Neutron generator  $\alpha$ -Be.


Only a bubble detector can be used in this scheme because of long count times, and the absolute zero false bubbles.

Fig.4 Bubbles captured from fast neutron exposure to the DU target while it was being bombarded *with slow neutrons*.






**Fig.5 Bubble detector test using only the slowed neutrons, without the DU target shows 5 or 6 small bubbles during an identical measured time period. Note that the two larger bubbles in this picture were there before the test was run so must be disregarded.**



**Fig. 6 A test showing fast neutrons captured right next to the bare source, that is no moderator. There were 8 bubbles left in the BTI from previous tests, so they should be disregarded in the total count here. These include those two large bubbles, which did not disappear upon re-pressurization of the detector.**



***Bubble detector test without any source, without ant DU, yields no bubbles.***

**note 1** - USA laws and rules allow for up to 15 pounds of DU metal without a license, nor

is there any restriction on the number of Radium Watch hands that can be owned.

**note 2:**

Some other possible fission products (among many) -

$U-235 + n = Ba-144 + Kr-90 + 2n + \text{energy}$

$U-235 + n = Ba-141 + Kr-92 + 3n + 170 \text{ MeV}$

$U-235 + n = Zr-94 + Te-139 + 3n + 197 \text{ MeV}$

**Have Fun**

**George Dowell, "Geo"**

---

*NLNL/ New London Nucleonics Laboratory*

*Copyright © Viscom Inc. 2007-2019*

*The treatise may under no circumstances be resold or redistributed in either printed, electronic, or any other forms, without prior written permission from the author*

*Comments, criticism and questions will be appreciated and may be directed to the author by email to [GEOelectronics@Rallstech.net](mailto:GEOelectronics@Rallstech.net)*

*All PHOTOS © by the author unless noted otherwise*

